

MIB (Management Information Base) Reference List

9-Jun-10

OID	TAG Name	Data Type	Data size	Access	SET Summary
1.3.6.1.4.1.2699.1.4.1.2.1	pdmGeneralProductName	OCTET STRING	255 byte	R	GET: Get "NEC/model name".
1.3.6.1.4.1.2699.1.4.1.2.2	pdmGeneralSerialNumber	OCTET STRING	255 byte	R	GET: Get <i>Serial number</i> .
1.3.6.1.4.1.2699.1.4.1.2.3	pdmGeneralAssetTag	OCTET STRING	63 byte	R/W	GET: Get the user set <i>Asset Tag</i> strings or SPACE, if no strings is set. SET: Set <i>Asset Tag</i> ASCII strings.
1.3.6.1.4.1.2699.1.4.1.2.4	pdmGeneralHardwareVersion	OCTET STRING	255 byte	R	GET: Get SPACE always.
1.3.6.1.4.1.2699.1.4.1.2.5	pdmGeneralServicePerson	OCTET STRING	255 byte	R/W	GET: Get SPACE always. SET: Unsupported.
1.3.6.1.4.1.2699.1.4.1.2.6	pdmGeneralDeviceAge	Counter32	4 byte	R	GET: Get the time of power on period at the 30 minutes intervals in the range of 0 - 65535.
1.3.6.1.4.1.2699.1.4.1.2.7	pdmGeneralPowerOnCount	Counter32	4 byte	R	GET: Get <i>Power ON COUNT</i> in the range of 0 - 65535.
1.3.6.1.4.1.2699.1.4.1.2.8	pdmGeneralManufactureDate	OCTET STRING	255 byte	R	GET: Get SPACE always.
1.3.6.1.4.1.2699.1.4.1.2.9	pdmGeneralLanguageTagSNMP	OCTET STRING	63 byte	R/W	GET: Get "en-US" always. SET: Unsupported.
1.3.6.1.4.1.2699.1.4.1.2.10	pdmGeneralNtpServerAddress	OCTET STRING	255 byte	R/W	GET: Get " <i>IP Address</i> " is stored in the device.If any address isn't stored, get "000.000.000.000". SET: Set " <i>IP Address</i> " to device.(Store only) NOTE: This device doesn't support to put a clock right automatically.
1.3.6.1.4.1.2699.1.4.1.3.1.1.2	pdmCtrlrDescription	OCTET STRING	255 byte	R	GET: Get <i>error</i> always.
1.3.6.1.4.1.2699.1.4.1.3.1.1.3	pdmCtrlrHardwareVersion	OCTET STRING	255 byte	R	GET: Get <i>error</i> always.
1.3.6.1.4.1.2699.1.4.1.3.1.1.4	pdmCtrlrFirmwareVersion	OCTET STRING	255 byte	R	GET: Get <i>error</i> always.
1.3.6.1.4.1.2699.1.4.1.3.1.1.5	pdmCtrlrFirmwareUpgradeable	INTEGER	4 byte	R	GET: Get "unknown(2)" always.
1.3.6.1.4.1.2699.1.4.1.3.1.1.6	pdmCtrlrUpgradeInstructions	OCTET STRING	255 byte	R/W	GET: Get SPACE always. SET: Unsupported.
1.3.6.1.4.1.2699.1.4.1.3.1.1.7	pdmCtrlrPostStatus	INTEGER	4 byte	R	GET: Get "unknown(2)" always.
1.3.6.1.4.1.2699.1.4.1.3.1.1.8	pdmCtrlrPostCode	Integer32	4 byte	R	GET: Get "0 (zero)" always.
1.3.6.1.4.1.2699.1.4.1.3.1.1.9	pdmCtrlrPostStatusDefinitions	OCTET STRING	255 byte	R	GET: Get SPACE always.
1.3.6.1.4.1.2699.1.4.1.4.1.1.2	pdmPowerImplementedState	INTEGER	4 byte	R	GET: Get current power status as; Power ON state: ON(11), Power save state: PowerSave(8), Stand-by state: Standby(7).
1.3.6.1.4.1.2699.1.4.1.4.1.1.3	pdmPowerDescription	OCTET STRING	255 byte	R	GET: Get <i>error</i> always.
1.3.6.1.4.1.2699.1.4.1.4.1.1.4	pdmPowerMfrDescription	OCTET STRING	255 byte	R	GET: Get <i>error</i> always.
1.3.6.1.4.1.2699.1.4.1.4.1.1.5	pdmPowerTargetState	INTEGER	4 byte	R	GET: Get "noTransition(3)" always.
1.3.6.1.4.1.2699.1.4.1.4.1.1.6	pdmPowerTransitionTime	Integer32	4 byte	R	GET: Get "-2 (unknown) : always.
1.3.6.1.4.1.2699.1.4.1.4.1.1.7	pdmPowerCommAvailable	INTEGER	4 byte	R	GET: Get "notAvailable(4)", if the device is executing AUTO SETUP or RESET function, otherwise get Available(3).
1.3.6.1.4.1.2699.1.4.1.4.2	pdmPowerCurrentState	INTEGER	4 byte	R	GET: Get current power status as; Power ON state: ON(11), Power save state: PowerSave(8), Stand-by state: Standby(7).
1.3.6.1.4.1.2699.1.4.1.4.3	pdmPowerRequestedState	INTEGER	4 byte	R/W	GET: Get current power status as; Power ON state: ON(11), Power save state: PowerSave(8), Stand-by state: Standby(7). SET: Set to change the power status as; ON(11): Power ON state, Standby(7): Stand-by state .
1.3.6.1.4.1.2699.1.4.1.5.1	pdmDisplayCapResolutionH	Integer32	4 byte	R	GET: Get "0 (zero)" always.
1.3.6.1.4.1.2699.1.4.1.5.2	pdmDisplayCapResolutionV	Integer32	4 byte	R	GET: Get "0 (zero)" always.
1.3.6.1.4.1.2699.1.4.1.5.3	pdmDisplayCapPhysSizeH	Integer32	4 byte	R	GET: Get "0 (zero)" always.
1.3.6.1.4.1.2699.1.4.1.5.4	pdmDisplayCapPhysSizeV	Integer32	4 byte	R	GET: Get "0 (zero)" always.
1.3.6.1.4.1.2699.1.4.1.6.1.1.2	pdmDisplaySetAffectsAll	INTEGER	4 byte	R	Unsupported.
1.3.6.1.4.1.2699.1.4.1.6.1.1.3	pdmDisplaySetInputSource	Integer32	4 byte	R/W	GET: Get current input source. SET: Set to change input source; VGA(1), RGB/HV(2), DVI(3), HDMI(4 or 17), VIDEO1(5), VIDEO2(6), S-VIDEO(7), TV(10), DVD/HD1(12), OPTION(13), DVD/HD2(14), DisplayPort(15)
1.3.6.1.4.1.2699.1.4.1.6.1.1.4	pdmDisplaySetBrightness	Integer32	4 byte	R/W	GET: Get current <i>Brightness</i> value (0 - 100). SET: Set to change the <i>Brightness</i> value (0 - 100).
1.3.6.1.4.1.2699.1.4.1.6.1.1.5	pdmDisplaySetBrtnMax	Integer32	4 byte	R	GET: Get the <i>Brightness</i> maximum value (100).
1.3.6.1.4.1.2699.1.4.1.6.1.1.6	pdmDisplaySetContrast	Integer32	4 byte	R/W	GET: Get current <i>Contrast</i> value (0 - 64). SET: Set to change the <i>Contrast</i> value (0 - 64).

1.3.6.1.4.1.2699.1.4.1.6.1.1.7	pdmDisplaySetConMax	Integer32	4 byte	R	GET: Get the <i>Contrast</i> maximum value (64).
1.3.6.1.4.1.2699.1.4.1.6.1.1.8	pdmDisplaySetRed	Integer32	4 byte	R/W	Unsupported.
1.3.6.1.4.1.2699.1.4.1.6.1.1.9	pdmDisplaySetGreen	Integer32	4 byte	R/W	Unsupported.
1.3.6.1.4.1.2699.1.4.1.6.1.1.10	pdmDisplaySetBlue	Integer32	4 byte	R/W	Unsupported.
1.3.6.1.4.1.2699.1.4.1.6.1.1.11	pdmDisplaySetRGBMax	Integer32	4 byte	R	Unsupported.
1.3.6.1.4.1.2699.1.4.1.6.1.1.12	pdmDisplaySetSaturation	Integer32	4 byte	R/W	GET: Get current <i>Saturation</i> value (0 - 63). SET: Set to change the <i>Saturation</i> value (0 - 63).
1.3.6.1.4.1.2699.1.4.1.6.1.1.13	pdmDisplaySetSatMax	Integer32	4 byte	R	GET: Get the <i>Saturation</i> maximum value (63).
1.3.6.1.4.1.2699.1.4.1.6.1.1.14	pdmDisplaySetHue	Integer32	4 byte	R/W	GET: Get current <i>Hue</i> value (0 - 63). SET: Set to change the <i>Hue</i> value (0 - 63).
1.3.6.1.4.1.2699.1.4.1.6.1.1.15	pdmDisplaySetHueMax	Integer32	4 byte	R	GET: Get the <i>Hue</i> maximum value (63).
1.3.6.1.4.1.2699.1.4.1.6.1.1.16	pdmDisplaySetSharpness	Integer32	4 byte	R/W	GET: Get current <i>Sharpness</i> value (0 - 82). SET: Set to change the <i>Sharpness</i> value (0 - 82).
1.3.6.1.4.1.2699.1.4.1.6.1.1.17	pdmDisplaySetShpMax	Integer32	4 byte	R	GET: Get the <i>Sharpness</i> maximum value (82).
1.3.6.1.4.1.2699.1.4.1.6.1.1.18	pdmDisplaySetColorTemp	INTEGER	4 byte	R/W	GET: Get current color temperature setting as; 10000K: unknown(2), CUSTOM: userDefined(3). SET: Set to change the color temperature as; unknown(2): 10000K, userDefined(3): CUSTOM.
1.3.6.1.4.1.2699.1.4.1.6.1.1.19	pdmDisplaySetRedClrTmp	Integer32	4 byte	R/W	GET: Get current color temperature red value (0 - 255). SET: Set the color temperature red value (0 - 255). Note) This control valid for the condition of "pdmDisplaySetColorTemp is set to userDefined(3)".
1.3.6.1.4.1.2699.1.4.1.6.1.1.20	pdmDisplaySetGreenClrTmp	Integer32	4 byte	R/W	GET: Get current color temperature green value (0 - 255). SET: Set the color temperature green value (0 - 255). Note) This control valid for the condition of "pdmDisplaySetColorTemp is set to userDefined(3)".
1.3.6.1.4.1.2699.1.4.1.6.1.1.21	pdmDisplaySetBlueClrTmp	Integer32	4 byte	R/W	GET: Get current color temperature blue value (0 - 255). SET: Set the color temperature blue value (0 - 255). Note) This control valid for the condition of "pdmDisplaySetColorTemp is set to userDefined(3)".
1.3.6.1.4.1.2699.1.4.1.6.1.1.22	pdmDisplaySetClrTmpMax	Integer32	4 byte	R	GET: Get current color temperature value (255). Note) This control valid for the condition of "pdmDisplaySetColorTemp is set to userDefined(3)".
1.3.6.1.4.1.2699.1.4.1.6.2	pdmDisplaySetVideoMute	INTEGER	4 byte	R/W	Unsupported.
1.3.6.1.4.1.2699.1.4.1.6.3	pdmDisplaySetDisplayMode	INTEGER	4 byte	R/W	GET: Get current <i>Display Mode</i> as; NORMAL: Windows4x3(7), FULL: FullScreen(9), WIDE: WideScreen16x9(5), ZOOM: Zoom(3). SET: Set the <i>Display Mode</i> as: letterbox16x9(4)/ crop(6)/ window4x3(7)/ fill4x3(8): NORMAL, widescreen16x9(5)/ stadium(10): WIDE, fullscreen(9)/ zoom(3): FULL.
1.3.6.1.4.1.2699.1.4.1.7.1.1.2	pdmLightSourceDescription	OCTET STRING	255 byte	R	GET: Get SPACE always.
1.3.6.1.4.1.2699.1.4.1.7.1.1.3	pdmLightSourceStatus	INTEGER	4 byte	R	GET: Get "failed(4)", if the device occurs "Inverter abnormality", otherwise get "unknown(2)".
1.3.6.1.4.1.2699.1.4.1.7.1.1.4	pdmLightSourceEcoSetting	INTEGER	4 byte	R/W	GET: Get "other(1)" always. SET: Unsupported.
1.3.6.1.4.1.2699.1.4.1.7.1.1.5	pdmLightSourceAge	Counter32	4 byte	R/W	GET: Get the time of power on period at the 30 minutes intervals in the range of 0 - 65535. SET: Unsupported.
1.3.6.1.4.1.2699.1.4.1.7.1.1.6	pdmLightSourceErrorCounter	Counter32	4 byte	R	GET: Get "0 (zero)" always.
1.3.6.1.4.1.2699.1.4.1.7.1.1.7	pdmLightSourceReset	INTEGER	4 byte	R/W	GET: Get "idle(1)" always. SET: Unsupported.
1.3.6.1.4.1.2699.1.4.1.7.1.1.8	pdmLightSourceReplacementCount	Counter32	4 byte	R	GET: Get "0 (zero)" always.
1.3.6.1.4.1.2699.1.4.1.7.1.1.9	pdmLightSourceReplacementTime	OCTET STRING	19 ~ 25 byte	R	GET: Get SPACE always.
1.3.6.1.4.1.2699.1.4.1.7.1.1.10	pdmLightSourceReplacementInterval	Integer32	4 byte	R/W	GET: Get "0 (zero)" always. SET: Unsupported.
1.3.6.1.4.1.2699.1.4.1.7.1.1.11	pdmLightSourceReplacementPN	OCTET STRING	255 byte	R/W	GET: Get SPACE always.
1.3.6.1.4.1.2699.1.4.1.8.1.1.2	pdmFanDescription	OCTET STRING	1 ~ 63 byte	R	GET: Get <i>error</i> always.
1.3.6.1.4.1.2699.1.4.1.8.1.1.3	pdmFanStatus	INTEGER	4 byte	R	GET: Get current FAN status as; Normal: okay(3) Not fewer than one of FAN1/FAN2/FAN3 is abnormal: tooSlowFail(6).
1.3.6.1.4.1.2699.1.4.1.8.1.1.4	pdmFanSpeed	Gauge32	4 byte	R	Unsupported.
1.3.6.1.4.1.2699.1.4.1.8.1.1.5	pdmFanErrorCounter	Counter32	4 byte	R	Unsupported.
1.3.6.1.4.1.2699.1.4.1.8.1.1.6	pdmFanReset	INTEGER	4 byte	R/W	Unsupported.
1.3.6.1.4.1.2699.1.4.1.8.1.1.7	pdmFanReplacementCount	Counter32	4 byte	R	Unsupported.

1.3.6.1.4.1.2699.1.4.1.8.1.1.8	pdmFanReplacementTime	OCTET STRING	19 ~ 25 byte	R	Unsupported.
1.3.6.1.4.1.2699.1.4.1.8.1.1.9	pdmFanReplacementInterval	Integer32	4 byte	R/W	Unsupported.
1.3.6.1.4.1.2699.1.4.1.8.1.1.10	pdmFanReplacementPartNumber	OCTET STRING	255 byte	R/W	Unsupported.
1.3.6.1.4.1.2699.1.4.1.9.1.1.2	pdmFilterDescription	OCTET STRING	63 byte	R	Unsupported.
1.3.6.1.4.1.2699.1.4.1.9.1.1.3	pdmFilterStatus	INTEGER	4 byte	R	Unsupported.
1.3.6.1.4.1.2699.1.4.1.9.1.1.4	pdmFilterErrorCounter	Counter32	4 byte	R	Unsupported.
1.3.6.1.4.1.2699.1.4.1.9.1.1.5	pdmFilterReset	INTEGER	4 byte	R/W	Unsupported.
1.3.6.1.4.1.2699.1.4.1.9.1.1.6	pdmFilterReplaceCount	Counter32	4 byte	R	Unsupported.
1.3.6.1.4.1.2699.1.4.1.9.1.1.7	pdmFilterReplaceTime	OCTET STRING	19 ~ 25 byte	R	Unsupported.
1.3.6.1.4.1.2699.1.4.1.9.1.1.8	pdmFilterReplaceInterval	Integer32	4 byte	R/W	Unsupported.
1.3.6.1.4.1.2699.1.4.1.9.1.1.9	pdmFilterReplacePN	OCTET STRING	255 byte	R/W	Unsupported.
1.3.6.1.4.1.2699.1.4.1.9.1.1.10	pdmFilterAirFlow	Gauge32	4 byte	R	Unsupported.
1.3.6.1.4.1.2699.1.4.1.10.1.1.2	pdmTempSensorDescription	OCTET STRING	255 byte	R	Unsupported.
1.3.6.1.4.1.2699.1.4.1.10.1.1.3	pdmTempSensorStatus	INTEGER	4 byte	R	Unsupported.
1.3.6.1.4.1.2699.1.4.1.10.1.1.4	pdmTempSensorTemp	Gauge32	4 byte	R	Unsupported.
1.3.6.1.4.1.2699.1.4.1.10.1.1.5	pdmTempSensorErrorCounter	Counter32	4 byte	R	Unsupported.
1.3.6.1.4.1.2699.1.4.1.10.1.1.6	pdmTempSensorReset	INTEGER	4 byte	R/W	Unsupported.
1.3.6.1.4.1.2699.1.4.1.10.1.1.7	pdmTempSensorReplaceCount	Counter32	4 byte	R	Unsupported.
1.3.6.1.4.1.2699.1.4.1.10.1.1.8	pdmTempSensorReplaceTime	OCTET STRING	19 ~ 25 byte	R	Unsupported.
1.3.6.1.4.1.2699.1.4.1.10.1.1.9	pdmTempSensorReplaceInterval	Integer32	4 byte	R/W	Unsupported.
1.3.6.1.4.1.2699.1.4.1.10.1.1.10	pdmTempSensorReplacePN	OCTET STRING	255 byte	R/W	Unsupported.
1.3.6.1.4.1.2699.1.4.1.11.1.1.2	pdmTempSwitchDescription	OCTET STRING	255 byte	R	Unsupported.
1.3.6.1.4.1.2699.1.4.1.11.1.1.3	pdmTempSwitchStatus	INTEGER	4 byte	R	Unsupported.
1.3.6.1.4.1.2699.1.4.1.11.1.1.4	pdmTempSwitchErrorCounter	Counter32	4 byte	R	Unsupported.
1.3.6.1.4.1.2699.1.4.1.11.1.1.5	pdmTempSwitchReset	INTEGER	4 byte	R/W	Unsupported.
1.3.6.1.4.1.2699.1.4.1.11.1.1.6	pdmTempSwitchReplaceCount	Counter32	4 byte	R	Unsupported.
1.3.6.1.4.1.2699.1.4.1.11.1.1.7	pdmTempSwitchReplaceTime	OCTET STRING	19 ~ 25 byte	R	Unsupported.
1.3.6.1.4.1.2699.1.4.1.11.1.1.8	pdmTempSwitchReplacePN	OCTET STRING	255 byte	R/W	Unsupported.
1.3.6.1.4.1.2699.1.4.1.12.1.1.2	pdmConnectorDescription	OCTET STRING	255 byte	R	GET: Get SPACE always.
1.3.6.1.4.1.2699.1.4.1.12.1.1.3	pdmConnectorType	INTEGER	4 byte	R	GET: Get current input as; VGA: vga(3), RGB/HV: other(1), DVI: dviD(4), HDMI: hdmi(6), VIDEO1: rcaPlugVideo3(13), S-VIDEO: sVideo(10), DisplayPort: displayPort(9), Others: unknown(2).
1.3.6.1.4.1.2699.1.4.1.12.1.1.4	pdmConnectorEnabled	INTEGER	4 byte	R/W	GET: Get "TRUE(1)" always. SET: Unsupported.
1.3.6.1.4.1.2699.1.4.1.12.1.1.5	pdmConnectorAudioAdjust	Integer32	4 byte	R/W	GET: Get "0 (zero)" always. SET: Unsupported.
1.3.6.1.4.1.2699.1.4.1.12.1.1.6	pdmConnectorVideoAdjust	Integer32	4 byte	R/W	GET: Get "0 (zero)" always. SET: Unsupported.
1.3.6.1.4.1.2699.1.4.1.12.2	pdmConnectorVideoCurrInput	Integer32	4 byte	R/W	GET: Get "0 (zero)" always. SET: Unsupported.
1.3.6.1.4.1.2699.1.4.1.12.3	pdmConnectorAudioCurrInput	Integer32	4 byte	R/W	GET: Get "0 (zero)" always. SET: Unsupported.
1.3.6.1.4.1.2699.1.4.1.13.1.1.2	pdmInterlockDescription	OCTET STRING	255 byte	R	Unsupported.
1.3.6.1.4.1.2699.1.4.1.13.1.1.3	pdmInterlockStatus	INTEGER	4 byte	R	Unsupported.
1.3.6.1.4.1.2699.1.4.1.14.1.1.2	pdmLocaleCharsetEnum	Integer32	4 byte	R	GET: Get "0 (zero)" always.
1.3.6.1.4.1.2699.1.4.1.14.2	pdmLocaleCharsetEnumEWS	Integer32	4 byte	R/W	GET: Get "0 (zero)" always. SET: Unsupported.
1.3.6.1.4.1.2699.1.4.1.15.1.1.2	pdmLocaleLanguageTag	OCTET STRING	63 byte	R	GET: Get SPACE always.
1.3.6.1.4.1.2699.1.4.1.15.2	pdmLocaleLanguageTagEWS	OCTET STRING	63 byte	R/W	GET: Get "US" always. SET: Unsupported.
1.3.6.1.4.1.2699.1.4.1.15.3	pdmLocaleLanguageTagOSD	OCTET STRING	63 byte	R/W	GET: Get SPACE always. SET: Unsupported.
1.3.6.1.4.1.2699.1.4.1.15.4	pdmLocaleLanguageTagWSM	OCTET STRING	63 byte	R/W	GET: Get SPACE always. SET: Unsupported.
1.3.6.1.4.1.2699.1.4.1.16.1	pdmAudioDescription	OCTET STRING	255 byte	R	GET: Get SPACE always.
1.3.6.1.4.1.2699.1.4.1.16.2	pdmAudioVolume	INTEGER	4 byte	R/W	GET: Get current Audio Volume value (0 - 100). SET: Set to change the Audio Volume value (0 - 100).

1.3.6.1.4.1.2699.1.4.1.16.3	pdmAudioMute	INTEGER	4 byte	R/W	GET: Get current <i>Audio Mute</i> condition as; MUTE: 1. MUTE CANCEL: 0. SET: Set to change <i>Audio Mute</i> condition as; 1: MUTE 0: MUTE CANCEL.
1.3.6.1.4.1.2699.1.4.1.16.4	pdmAudioTreble	Integer32	4 byte	R/W	GET: Get current <i>Audio Treble</i> value (0 - 100). SET: Set to change the <i>Audio Treble</i> value (0 - 100).
1.3.6.1.4.1.2699.1.4.1.16.5	pdmAudioBass	Integer32	4 byte	R/W	GET: Get current <i>Audio Bass</i> value (0 - 100). SET: Set to change the <i>Audio Bass</i> value (0 - 100).
1.3.6.1.4.1.2699.1.4.1.16.6	pdmAudioBalance	Integer32	4 byte	R/W	GET: Get current <i>Audio Balance</i> value (0 - 100). SET: Set to change the <i>Audio Balance</i> value (0 - 100).
1.3.6.1.4.1.2699.1.4.1.17.1.1.2	pdmButtonDescription	OCTET STRING	255 byte	R	GET: Get SPACE always.
1.3.6.1.4.1.2699.1.4.1.17.1.1.3	pdmButtonEnabled	INTEGER	4 byte	R/W	GET: Get the Control Panel Key Lock status as; UNLOCK: true(1), LOCK: false(2). SET: Set to change the Control Panel Key Lock status as; true(1): UNLOCK, false(2): LOCK.
1.3.6.1.4.1.2699.1.4.1.18.1.1.2	pdmAlertGroupType	OCTET STRING	255 byte	R	GET: Get the error status when it has one error, as; Power supply is abnormal: "7X POWER", FAN is abnormal: "8X FAN", Inverter is abnormal: "9X INVERTER" Temperature is abnormal: "AX TEMPERATURE". If it has two or more errors, get "General".
1.3.6.1.4.1.2699.1.4.1.18.1.1.3	pdmAlertGroupId	OCTET STRING	255 byte	R	GET: Get the error status as; Standby-power +3.3V abnormality: "Power_0", Standby-power +5V abnormality: "Power_1", Panel-power +12V abnormality: "Power_2", Main-power +2.5V abnormality: "Power_3", Main-power +1.8V abnormality: "Power_4", Main-power +5V abnormality: "Power_5", Sub-power +3.3V abnormality: "Power_6", Main-power +3.3V abnormality: "Power_7", Cooling fan-1 abnormality: "Fan_0", Cooling fan-2 abnormality: "Fan_1", Cooling fan-3 abnormality: "Fan_2", Inverter abnormality: "Inverter_0", Temperature abnormality – shutdown: "Temperature_0", Temperature abnormality – half brightness: "Temperature_1".
1.3.6.1.4.1.2699.1.4.1.18.1.1.4	pdmAlertCode	Integer32	4 byte	R	GET: Get the error status as; Standby-power +3.3V abnormality: 70h, Standby-power +5V abnormality: 71h, Panel-power +12V abnormality: 72h, Main-power +2.5V abnormality: 73h, Main-power +1.8V abnormality: 74h, Main-power +5V abnormality: 75h, Sub-power +3.3V abnormality: 76h, Main-power +3.3V abnormality: 77h, Cooling fan-1 abnormality: 80h, Cooling fan-2 abnormality: 81h, Cooling fan-3 abnormality: 82h, Inverter abnormality: 90h, Temperature abnormality – shutdown: A0h, Temperature abnormality – half brightness: A1h.
1.3.6.1.4.1.2699.1.4.1.18.1.1.5	pdmAlertDescription	OCTET STRING	255 byte	R	GET: Get SPACE always.
1.3.6.1.4.1.2699.1.4.1.18.1.1.6	pdmAlertSeverityLevel	INTEGER	4 byte	R	GET: Get "warning(4)" always.
1.3.6.1.4.1.2699.1.4.1.18.1.1.7	pdmAlertTrainingLevel	INTEGER	4 byte	R	GET: Get "unknown(2)" always.
1.3.6.1.4.1.2699.1.4.1.18.1.1.8	pdmAlertDateTime	OCTET STRING	25 byte	R	GET: Get "1980-01-01T00:00:00" always.
1.3.6.1.4.1.2699.1.4.1.18.1.1.9	pdmAlertPowerOnCount	Counter32	4 byte	R	GET: Get "0 (zero)" always.
1.3.6.1.4.1.2699.1.4.1.18.1.1.10	pdmAlertSysUptime	TimeTicks		R	GET: Get "0 (zero)" always.
1.3.6.1.4.1.2699.1.4.1.18.2	pdmAlertCriticalAlertsCount	Counter32	4 byte	R	GET: Get "0 (zero)" always.
1.3.6.1.4.1.2699.1.4.1.18.3	pdmAlertAllAlertsCount	Counter32	4 byte	R	GET: Get "0 (zero)" always.

How to get PDM-MIB: Please contact the sales company/ deviation you purchased.

All data are subject to change without notice.